

Widgets gallery


Widgets are graphical objects to visualize data from [End View](#) of objects and links.

Add widget ↗ test_rel /Root/test_rel ✕


Counter

46


Ring


37%
demo.metric


Level


78%
demo.metric


Circle




Radial




Chart




Structure



Section



Button


demoOperation

Object/Link:

Metric name:

Show label

Label text:

Value type:

Abbreviated value

Theme:


Dictionary:



=

Widget can be added to any object with the data from any other object in the system to create dashboards or reports.


Widgets are displayed:

- on the object they have been added (in [Standard View](#));
- in the link pop-up window;
- and in their [Widgets](#) sections:







Object info: Memory



To add new widget:



- press  button in Breadcrumbs panel;
- choose widget type;
- choose the object you would like to get data from (the default is the current object);
- and metric or graph to display;
- set widget specific parameters:


Add widget  Memory /Root/Staging/Memory ✕

Counter

58.03


MEM.percentUsed

Ring




96%

Level




22%

Circle




41% 45% 14%

Radial




100 80 90

Chart




150 125 100 75 50

Structure




Section




Agent data

Button



Object/Link:

 Memory /Root/Staging/Memory

Metric name:

MEM.percentUsed

|

-- Not selected --

SWAP.memoryType

SWAP.bytesTotal

SWAP.bytesUsed

SWAP.bytesAvailable

SWAP.percentUsed

TOTAL.memoryType

TOTAL.bytesTotal

TOTAL.bytesUsed

TOTAL.bytesAvailable

TOTAL.percentUsed

MEM.memoryType

MEM.bytesTotal

MEM.bytesUsed

MEM.bytesAvailable

MEM.percentUsed

Standard


Add Cancel

To edit or delete a widget:

- place cursor over the widget;
- wait for edit and delete buttons to appear;
- press the respective button.

To reorder widgets just drag-and-drop one.

For most of widgets, e.g. *Counter* and *Ring*, it is possible to hide and change label text (name of the metric) and display min/avg/max value, its count, sum and deviation for period:


Add widget  Memory /Root/Staging/Memory ✕

Counter

58.95

Mem used, %


Ring



47 %

demo.metric


Level



50%


demo.metric

Circle




33% 9% 58%

Radial




100

Chart




160
140
120
100


Structure



Section



Button



demoOperation

Object/Link:

Metric name:

Show label YES

Label text:

Value type:

Abbreviated value NO

Theme:

Dictionary:

^

Key = Value

Sometimes it is required to publish a widget on an external site. To do this:

- hover your mouse over the widget;
- click on an appeared icon "Widget code";
- copy and paste HTML-code on your page.

For embedded widgets of counters and graphs, the following data is available, which are saved when the widget is published on an external site:

- manual period setting;
- header setting.

- Counter
- Ring
- Level
- Circle
- Radial
- Chart
- Structure
- Section
- Button